

Wireless Networking with KWiFiManager

# WORKING WIRELESS

Connecting to wireless networks is more popular than ever. KDE's KWiFiManager is a handy tool for monitoring and managing wireless connections.

BY CHRIS HOWELLS

**W**ireless networks are a very valuable addition to modern day computing. Wireless technology makes it easy to set up the network, and users can get online from a growing number of places, including pubs, train stations, libraries, and airports.

Although a wireless network is physically easier to install than a wired network, the software side of a wireless network is frequently harder to configure. For instance, for each wireless network connection, you must select the correct network name – commonly referred to as SSID (Service Set Identifier) – and you must specify whether to use encryption. If you are using encryption with the connection, you must specify the right WEP

(Wired Equivalent Privacy) key. KDE's KWiFiManager utility helps you manage these and other wireless network settings and also monitors your wireless network connections.

## Introducing KWiFiManager

KWiFiManager is part of the main KDE distribution, and as such, if you have KDE installed on your computer, KWiFiManager will probably also be installed already. If you don't already have KWiFiManager, use your Linux distribution's package management tool to install the *kdenetwork* package. Some distributions package KWiFiManager on its own, not as part of the *kdenetwork* package, so in that case, look for a package with a name similar to "kwifimanager."

Generally, KWiFiManager should work with any 802.11a, 802.11b, or 802.11g wireless network adapter for which there are Linux drivers. Frequently with modern Linux distributions and a PCMCIA/USB 802.11b card, all that is required is to plug the adapter in, and Hotplug will take care of the rest. Otherwise, it is best to consult the documentation for your distribution – the distribution's hardware management tool will often allow you to set up the driver.

When you first start KWiFiManager, you'll see a display similar to Figure 1. The main window gives the status of the active wireless connection. The *Scan for Networks* button initiates a scan that determines if you are in the range of a wireless network. The *Settings* menu



you will need to ask the system administrator for details. In a public place such as a station or airport, WEP will not be enabled, and you will need to scan for available networks to find out the SSID – it will vary depending on which company is running the wireless network.

Scanning for all wireless networks is easy using KWiFiManager. Simply load KWiFiManager from the KMenu or by running *kwifimanager*. Click the *Scan for Networks* button (refer to Figure 1). A window will appear, giving the list of all networks nearby. If the wireless signal is a little weak, the *Acoustic Scanning* feature (under the Settings menu) can help to locate a stronger signal.

In *Acoustic Scanning* mode, KWiFiManager will periodically emit a tone. The higher the pitch of the tone, the stronger the wireless signal, and consequently, the higher the likelihood of a successful connection. Therefore, if there are problems with the connection and KWiFiManager emits only a low pitch, it might be a good idea to wander around a little bit until the pitch rises.

Now that the name of the wireless network is known, you can use KWiFiManager to connect to it.

### Connecting to a Wireless Network

KWiFiManager lets you pre-define network connection configurations. This feature is very useful if you travel to different locations, for example, if you roam between your home, your office, and another network.

To configure a connection, load KWiFiManager from the KMenu and choose *Settings/Configuration Editor* option (see Figure 2). You'll need to enter the administrator (root) password in order to proceed, since the control panel will need to have root privileges to make configuration changes to the system.

One of the most important settings on this page is the Network name setting, where you will enter the SSID. Most wireless networks are based around an access point, and, in this case, the Operation mode should be set to *Managed*. However if there is no access point and you are simply connecting to other computers with wireless network cards, the mode should be set to *Ad-Hoc*.

Generally, the speed should be set to *Auto*. The *Auto* setting means that,




Figure 2: The KWiFiManager configuration editor.

when the signal is weak, the wireless card will automatically fall back to lower speeds in an attempt to facilitate communications. If the signal strength increases again, the speed should increase again. However, if an attempt is made to force a high speed and the signal becomes weak, the wireless card may fail to transfer any data due to transmission errors.

In the wireless networking world, DHCP (Dynamic Host Configuration Protocol) is typically used to configure the network interface. If this is the case for your network, you can enter */sbin/dhclient* in the *Execute script on connect* combo box. The network interface will then be configured automatically once the connection to the access point has been made.

The *Enable power management* setting (shown in Figure 2) can be very useful for laptops. In the case that the signal strength from the access point is strong,

(shown in Figure 1) leads to settings that help you configure and manage your wireless connections.

### Finding Wireless Networks

In order to connect to a wireless network, you must know the SSID for the network and whether WEP is in use or not. In a location such as an office, WEP will almost certainly be enabled, and




Figure 1: The KWiFiManager main window.

### Wireless Network Encryption

Wireless networks usually use the WEP system to ensure that outside users can't eavesdrop on wireless communications. WEP is particularly important if data is being sent over a protocol that is not itself encrypted.

In the past, WEP rightfully received a lot of bad press. In part, this bad press was because the first generation of wireless products contained a particularly poor implementation of WEP that allowed a brute force attack to be carried out against the encryption key when a sufficiently large number of data packets had been sampled. This risk is now lower, though a new encryption standard called WPA (Wi-Fi Protected Access) is starting to be introduced.

